
JACK Audio Connection Kit (JACK) Client for Python

Release 0.5.4

Matthias Geier

2022-06-04

Contents

1	Installation	2
1.1	Requirements	2
2	Usage	3
3	Example Programs	5
3.1	Chatty Client	5
3.2	Pass-Through Client	7
3.3	Sound File Playback	9
3.4	“Showtime” Client	11
3.5	MIDI Monitor	12
3.6	MIDI Chord Generator	12
3.7	MIDI File Player	13
3.8	Simple MIDI Synth	15
3.9	Simple MIDI Synth (NumPy Edition)	17
4	API Documentation	20
5	Contributing	45
6	Version History	46
7	Other Python Modules for JACK	48
7.1	JACK Client	48
7.2	JACK Server	48
7.3	D-Bus Interface (JACK2 only)	48

This Python module (named `jack`) provides bindings for the [JACK¹](https://jackaudio.org/) library.

Documentation:

<https://jackclient-python.readthedocs.io/>

Source code and issue tracker:

<https://github.com/spatialaudio/jackclient-python/>

License:

MIT – see the file `LICENSE` for details.

¹ <https://jackaudio.org/>

1 Installation

² You can use `pip` to install the `jack` module:

```
python3 -m pip install JACK-Client
```

Depending on your Python installation (see [Requirements](#) below), you may have to use `python` instead of `python3`. If you have installed the module already, you can use the `--upgrade` flag to get the newest release.

To un-install, use:

```
python3 -m pip uninstall JACK-Client
```

1.1 Requirements

You'll need some software packages in order to install and use the `jack` module. Some of those might already be installed on your system and some are automatically installed when you use the aforementioned `pip` command.

Python:

Of course, you'll need [Python](#)³. More specifically, you'll need Python 3. If you don't have Python installed yet, you should get one of the distributions which already include CFFI and NumPy (and many other useful things), e.g. [Anaconda](#)⁴ or [WinPython](#)⁵.

pip/setuptools:

Those are needed for the installation of the Python module and its dependencies. Most systems will have these installed already, but if not, you should install it with your package manager or you can download and install `pip` and `setuptools` as described on the [pip installation](#)⁶ page. If you happen to have `pip` but not `setuptools`, use this command:

```
python3 -m pip install setuptools
```

To upgrade to a newer version of an already installed package (including `pip` itself), use the `--upgrade` flag.

CFFI:

The [C Foreign Function Interface for Python](#)⁷ is used to access the C-API of the JACK library from within Python. It is supported on CPython and is distributed with [PyPy](#)⁸. It will be automatically installed when installing the `JACK-Client` package with `pip`. If you prefer, you can also install it with your package manager (the package might be called `python3-cffi` or similar).

JACK library:

The [JACK](#)⁹ library must be installed on your system (and CFFI must be able to find it). Again, you should use your package manager to install it. Make sure you install the JACK daemon (called `jackd`). This will also install the JACK library package. If you don't have a package manager, you can try one of the binary installers from the [JACK download page](#)¹⁰. If you prefer, you can of course also download the sources and compile everything locally.

² <https://pypi.org/project/JACK-Client/>

³ <https://www.python.org/>

⁴ <https://www.anaconda.com/products/individual#Downloads>

⁵ <http://winpython.github.io/>

⁶ <https://pip.pypa.io/en/latest/installing/>

⁷ <https://cffi.readthedocs.org/>

⁸ <https://www.pypy.org/>

⁹ <https://jackaudio.org/>

¹⁰ <https://jackaudio.org/downloads/>

NumPy (optional):

NumPy¹¹ is only needed if you want to access the input and output buffers in the process callback as NumPy arrays. The only place where NumPy is needed is `jack.OwnerPort.get_array()` (and you can use `jack.OwnerPort.get_buffer()` as a NumPy-less alternative). If you need NumPy, you can install it with your package manager or use a Python distribution that already includes NumPy (see above). You can also install NumPy with pip, but depending on your platform, this might require a compiler and several additional libraries:

```
python3 -m pip install NumPy
```

2 Usage

First, import the module:

```
>>> import jack
```

Then, you most likely want to create a new `jack.Client`:

```
>>> client = jack.Client('MyGreatClient')
```

You probably want to create some audio input and output ports, too:

```
>>> client.inports.register('input_1')
jack.OwnerPort('MyGreatClient:input_1')
>>> client.outports.register('output_1')
jack.OwnerPort('MyGreatClient:output_1')
```

As you can see, these functions return the newly created port. If you want, you can save it for later:

```
>>> in2 = client.inports.register('input_2')
>>> out2 = client.outports.register('output_2')
```

To see what you can do with the returned objects, have a look at the documentation of the class `jack.OwnerPort`.

In case you forgot, you should remind yourself about the ports you just created:

```
>>> client.inports
[jack.OwnerPort('MyGreatClient:input_1'), jack.OwnerPort('MyGreatClient:input_2')]
>>> client.outports
[jack.OwnerPort('MyGreatClient:output_1'), jack.OwnerPort('MyGreatClient:output_2')]
```

Have a look at the documentation of the class `jack.Ports` to get more detailed information about these lists of ports.

If you have selected an appropriate driver in your JACK settings, you can also create MIDI ports:

```
>>> client.midi_inports.register('midi_in')
jack.OwnerMidiPort('MyGreatClient:midi_in')
>>> client.midi_outports.register('midi_out')
jack.OwnerMidiPort('MyGreatClient:midi_out')
```

You can check what other JACK ports are available (your output may be different):

```
>>> client.get_ports()
[jack.Port('system:capture_1'),
 jack.Port('system:capture_2'),
```

(continues on next page)

¹¹ <https://numpy.org/>

```

jack.Port('system:playback_1'),
jack.Port('system:playback_2'),
jack.MidiPort('system:midi_capture_1'),
jack.MidiPort('system:midi_playback_1'),
jack.OwnPort('MyGreatClient:input_1'),
jack.OwnPort('MyGreatClient:output_1'),
jack.OwnPort('MyGreatClient:input_2'),
jack.OwnPort('MyGreatClient:output_2'),
jack.OwnMidiPort('MyGreatClient:midi_in'),
jack.OwnMidiPort('MyGreatClient:midi_out')]

```

Note that the ports you created yourself are of type `jack.OwnPort` and `jack.OwnMidiPort`, while other ports are merely of type `jack.Port` and `jack.MidiPort`, respectively.

You can also be more specific when looking for ports:

```

>>> client.get_ports(is_audio=True, is_output=True, is_physical=True)
[jack.Port('system:capture_1'), jack.Port('system:capture_2')]

```

You can even use regular expressions to search for ports:

```

>>> client.get_ports('Great.*2$')
[jack.OwnPort('MyGreatClient:input_2'), jack.OwnPort('MyGreatClient:output_2')]

```

If you want, you can also set all kinds of callback functions for your client. For details see the documentation for the class `jack.Client` and the example applications in the `examples/` directory.

Once you are ready to run, you should activate your client:

```

>>> client.activate()

```

As soon as the client is activated, you can make connections (this isn't possible before activating the client):

```

>>> client.connect('system:capture_1', 'MyGreatClient:input_1')
>>> client.connect('MyGreatClient:output_1', 'system:playback_1')

```

You can also use the port objects from before instead of port names:

```

>>> client.connect(out2, 'system:playback_2')
>>> in2.connect('system:capture_2')

```

Use `jack.Client.get_all_connections()` to find out which other ports are connected to a given port. If you own the port, you can also use `jack.OwnPort.connections`.

```

>>> client.get_all_connections('system:playback_1')
[jack.OwnPort('MyGreatClient:output_1')]
>>> out2.connections
[jack.Port('system:playback_2')]

```

Of course you can also disconnect ports, there are again several possibilities:

```

>>> client.disconnect('system:capture_1', 'MyGreatClient:input_1')
>>> client.disconnect(out2, 'system:playback_2')
>>> in2.disconnect() # disconnect all connections with in2

```

If you don't need your ports anymore, you can un-register them:

```

>>> in2.unregister()
>>> client.outports.clear() # unregister all audio output ports

```

Finally, you can de-activate your JACK client and close it:

```
>>> client.deactivate()
>>> client.close()
```

3 Example Programs

3.1 Chatty Client

chatty_client.py

```
#!/usr/bin/env python3

"""Create a JACK client that prints a lot of information.

This client registers all possible callbacks (except the process
callback and the timebase callback, which would be just too much noise)
and prints some information whenever they are called.

"""

import jack

print('setting error/info functions')

@jack.set_error_function
def error(msg):
    print('Error:', msg)

@jack.set_info_function
def info(msg):
    print('Info:', msg)

print('starting chatty client')

client = jack.Client('Chatty-Client')

if client.status.server_started:
    print('JACK server was started')
else:
    print('JACK server was already running')
if client.status.name_not_unique:
    print('unique client name generated:', client.name)

print('registering callbacks')

@client.set_shutdown_callback
def shutdown(status, reason):
    print('JACK shutdown!')
    print('status:', status)
    print('reason:', reason)
```

(continues on next page)

```

@client.set_freewheel_callback
def freewheel(starting):
    print(['stopping', 'starting'][starting], 'freewheel mode')

@client.set_blocksize_callback
def blocksize(blocksize):
    print('setting blocksize to', blocksize)

@client.set_samplerate_callback
def samplerate(samplerate):
    print('setting samplerate to', samplerate)

@client.set_client_registration_callback
def client_registration(name, register):
    print('client', repr(name), ['unregistered', 'registered'][register])

@client.set_port_registration_callback
def port_registration(port, register):
    print(repr(port), ['unregistered', 'registered'][register])

@client.set_port_connect_callback
def port_connect(a, b, connect):
    print(['disconnected', 'connected'][connect], a, 'and', b)

try:
    @client.set_port_rename_callback
    def port_rename(port, old, new):
        print('renamed', port, 'from', repr(old), 'to', repr(new))
except AttributeError:
    print('Could not register port rename callback (not available on JACK1).')

@client.set_graph_order_callback
def graph_order():
    print('graph order changed')

@client.set_xrun_callback
def xrun(delay):
    print('xrun; delay', delay, 'microseconds')

try:
    @client.set_property_change_callback
    def property_change(subject, key, changed):
        print(f'subject {subject}: ', end='')
        if not key:
            assert changed == jack.PROPERTY_DELETED

```

```

        print('all properties were removed')
        return
    print('property {!r} was {}'.format(key, {
        jack.PROPERTY_CREATED: 'created',
        jack.PROPERTY_CHANGED: 'changed',
        jack.PROPERTY_DELETED: 'removed',
    }[changed]))
except jack.JackError as e:
    print(e)

print('activating JACK')
with client:
    print('#' * 80)
    print('press Return to quit')
    print('#' * 80)
    input()
    print('closing JACK')

```

3.2 Pass-Through Client

thru_client.py

```

#!/usr/bin/env python3

"""Create a JACK client that copies input audio directly to the outputs.

This is somewhat modeled after the "thru_client.c" example of JACK 2:
http://github.com/jackaudio/jack2/blob/master/example-clients/thru\_client.c

If you have a microphone and loudspeakers connected, this might cause an
acoustical feedback!

"""
```

```

import sys
import os
import jack
import threading

argv = iter(sys.argv)
# By default, use script name without extension as client name:
defaultclientname = os.path.splitext(os.path.basename(next(argv)))[0]
clientname = next(argv, defaultclientname)
servername = next(argv, None)

client = jack.Client(clientname, servername=servername)

if client.status.server_started:
    print('JACK server started')
if client.status.name_not_unique:
    print(f'unique name {client.name!r} assigned')

event = threading.Event()

```

(continues on next page)

```

@client.set_process_callback
def process(frames):
    assert len(client.inports) == len(client.outports)
    assert frames == client.blocksize
    for i, o in zip(client.inports, client.outports):
        o.get_buffer()[:] = i.get_buffer()

@client.set_shutdown_callback
def shutdown(status, reason):
    print('JACK shutdown!')
    print('status:', status)
    print('reason:', reason)
    event.set()

# create two port pairs
for number in 1, 2:
    client.inports.register(f'input_{number}')
    client.outports.register(f'output_{number}')

with client:
    # When entering this with-statement, client.activate() is called.
    # This tells the JACK server that we are ready to roll.
    # Our process() callback will start running now.

    # Connect the ports. You can't do this before the client is activated,
    # because we can't make connections to clients that aren't running.
    # Note the confusing (but necessary) orientation of the driver backend
    # ports: playback ports are "input" to the backend, and capture ports
    # are "output" from it.

    capture = client.get_ports(is_physical=True, is_output=True)
    if not capture:
        raise RuntimeError('No physical capture ports')

    for src, dest in zip(capture, client.inports):
        client.connect(src, dest)

    playback = client.get_ports(is_physical=True, is_input=True)
    if not playback:
        raise RuntimeError('No physical playback ports')

    for src, dest in zip(client.outports, playback):
        client.connect(src, dest)

    print('Press Ctrl+C to stop')
    try:
        event.wait()
    except KeyboardInterrupt:
        print('\nInterrupted by user')

# When the above with-statement is left (either because the end of the
# code block is reached, or because an exception was raised inside),
# client.deactivate() and client.close() are called automatically.

```


3.3 Sound File Playback

play_file.py

```
#!/usr/bin/env python3

"""Play a sound file.

This only reads a certain number of blocks at a time into memory,
therefore it can handle very long files and also files with many
channels.

NumPy and the soundfile module (http://PySoundFile.rtfld.io/) must be
installed for this to work.

"""
import argparse
try:
    import queue # Python 3.x
except ImportError:
    import Queue as queue # Python 2.x
import sys
import threading

parser = argparse.ArgumentParser(description=__doc__)
parser.add_argument('filename', help='audio file to be played back')
parser.add_argument(
    '-b', '--buffer-size', type=int, default=20,
    help='number of blocks used for buffering (default: %(default)s)')
parser.add_argument('-c', '--client-name', default='file player',
                    help='JACK client name')
parser.add_argument('-m', '--manual', action='store_true',
                    help="don't connect to output ports automatically")
args = parser.parse_args()
if args.buffer-size < 1:
    parser.error('buffer-size must be at least 1')

q = queue.Queue(maxsize=args.buffer-size)
event = threading.Event()

def print_error(*args):
    print(*args, file=sys.stderr)

def xrun(delay):
    print_error("An xrun occurred, increase JACK's period size?")

def shutdown(status, reason):
    print_error('JACK shutdown!')
    print_error('status:', status)
    print_error('reason:', reason)
    event.set()

def stop_callback(msg=''):

```

(continues on next page)

```

if msg:
    print_error(msg)
for port in client.outports:
    port.get_array().fill(0)
event.set()
raise jack.CallbackExit

def process(frames):
    if frames != blocksize:
        stop_callback('blocksize must not be changed, I quit!')
    try:
        data = q.get_nowait()
    except queue.Empty:
        stop_callback('Buffer is empty: increase buffersize?')
    if data is None:
        stop_callback() # Playback is finished
    for channel, port in zip(data.T, client.outports):
        port.get_array[:] = channel

try:
    import jack
    import soundfile as sf

    client = jack.Client(args.clientname)
    blocksize = client.blocksize
    samplerate = client.samplerate
    client.set_xrun_callback(xrun)
    client.set_shutdown_callback(shutdown)
    client.set_process_callback(process)

    with sf.SoundFile(args.filename) as f:
        for ch in range(f.channels):
            client.outports.register(f'out_{ch + 1}')
        block_generator = f.blocks(blocksize=blocksize, dtype='float32',
                                   always_2d=True, fill_value=0)
        for _, data in zip(range(args.buffersize), block_generator):
            q.put_nowait(data) # Pre-fill queue
        with client:
            if not args.manual:
                target_ports = client.get_ports(
                    is_physical=True, is_input=True, is_audio=True)
                if len(client.outports) == 1 and len(target_ports) > 1:
                    # Connect mono file to stereo output
                    client.outports[0].connect(target_ports[0])
                    client.outports[0].connect(target_ports[1])
                else:
                    for source, target in zip(client.outports, target_ports):
                        source.connect(target)
            timeout = blocksize * args.buffersize / samplerate
            for data in block_generator:
                q.put(data, timeout=timeout)
            q.put(None, timeout=timeout) # Signal end of file
            event.wait() # Wait until playback is finished
except KeyboardInterrupt:

```

```

    parser.exit('\nInterrupted by user')
except (queue.Full):
    # A timeout occurred, i.e. there was an error in the callback
    parser.exit(1)
except Exception as e:
    parser.exit(type(e).__name__ + ': ' + str(e))

```

3.4 “Showtime” Client

showtime.py

```

#!/usr/bin/env python3

"""Display information about time, transport state et cetera.

This is somewhat modeled after the "showtime.c" example of JACK.
https://github.com/jackaudio/example-clients/blob/master/showtime.c
https://github.com/jackaudio/jack2/blob/master/example-clients/showtime.c

"""
from contextlib import suppress
import time
import sys

import jack

try:
    client = jack.Client('showtime')
except jack.JackError:
    sys.exit('JACK server not running?')

def showtime():
    state, pos = client.transport_query()
    items = []
    items.append('frame = {} frame_time = {} usecs = {} '.format(
        pos['frame'], client.frame_time, pos['usecs']))
    items.append(f'state: {state}')
    with suppress(KeyError):
        items.append('BBT: {bar:3}|{beat}|{tick:04}'.format(**pos))
    with suppress(KeyError):
        items.append('TC: ({frame_time:.6f}, {next_time:.6f})'.format(**pos))
    with suppress(KeyError):
        items.append('BBT offset: ({bbt_offset})'.format(**pos))
    with suppress(KeyError):
        items.append(
            'audio/video: ({audio_frames_per_video_frame})'.format(**pos))
    with suppress(KeyError):
        video_offset = pos['video_offset']
        if video_offset:
            items.append(f' video@: ({video_offset})')
        else:
            items.append(' no video');
    print(*items, sep='\t')

```

(continues on next page)

```

@client.set_shutdown_callback
def shutdown(status, reason):
    sys.exit('JACK shut down, exiting ...')

with client:
    try:
        while True:
            time.sleep(0.00002)
            showtime()
    except KeyboardInterrupt:
        print('signal received, exiting ...', file=sys.stderr)
        sys.exit(0)

```

3.5 MIDI Monitor

midi_monitor.py

```

#!/usr/bin/env python3

"""JACK client that prints all received MIDI events."""

import jack
import binascii

client = jack.Client('MIDI-Monitor')
port = client.midi_inports.register('input')

@client.set_process_callback
def process(frames):
    for offset, data in port.incoming_midi_events():
        print('{}: 0x{}'.format(client.last_frame_time + offset,
                                binascii.hexlify(data).decode()))

with client:
    print('#' * 80)
    print('press Return to quit')
    print('#' * 80)
    input()

```

3.6 MIDI Chord Generator

midi_chords.py

```

#!/usr/bin/env python3

"""JACK client that creates minor triads from single MIDI notes.

All MIDI events are passed through.
Two additional events are created for each NoteOn and NoteOff event.

```

(continues on next page)

(continued from previous page)

```
"""
import jack
import struct

# First 4 bits of status byte:
NOTEON = 0x9
NOTEOFF = 0x8

INTERVALS = 3, 7 # minor triad

client = jack.Client('MIDI-Chord-Generator')
inport = client.midi_inports.register('input')
output = client.midi_outports.register('output')

@client.set_process_callback
def process(frames):
    output.clear_buffer()
    for offset, indata in inport.incoming_midi_events():
        # Note: This may raise an exception:
        output.write_midi_event(offset, indata) # pass through
        if len(indata) == 3:
            status, pitch, vel = struct.unpack('3B', indata)
            if status >> 4 in (NOTEON, NOTEOFF):
                for i in INTERVALS:
                    # Note: This may raise an exception:
                    output.write_midi_event(offset, (status, pitch + i, vel))

with client:
    print('#' * 80)
    print('press Return to quit')
    print('#' * 80)
    input()
```

3.7 MIDI File Player

midi_file_player.py

```
#!/usr/bin/env python3
"""Play a MIDI file.

This uses the "mido" module for handling MIDI: https://mido.readthedocs.io/

Pass the MIDI file name as first command line argument.

If a MIDI port name is passed as second argument, a connection is made.

"""
import sys
import threading

import jack
from mido import MidiFile

argv = iter(sys.argv)
```

(continues on next page)

```

next(argv)
filename = next(argv, '')
connect_to = next(argv, '')
if not filename:
    sys.exit('Please specify a MIDI file')
try:
    mid = iter(MidiFile(filename))
except Exception as e:
    sys.exit(type(e).__name__ + ' while loading MIDI: ' + str(e))

client = jack.Client('MIDI-File-Player')
port = client.midi_outports.register('output')
event = threading.Event()
msg = next(mid)
fs = None # sampling rate
offset = 0

@client.set_process_callback
def process(frames):
    global offset
    global msg
    port.clear_buffer()
    while True:
        if offset >= frames:
            offset -= frames
            return # We'll take care of this in the next block ...
        # Note: This may raise an exception:
        port.write_midi_event(offset, msg.bytes())
        try:
            msg = next(mid)
        except StopIteration:
            event.set()
            raise jack.CallbackExit
        offset += round(msg.time * fs)

@client.set_samplerate_callback
def samplerate(samplerate):
    global fs
    fs = samplerate

@client.set_shutdown_callback
def shutdown(status, reason):
    print('JACK shutdown:', reason, status)
    event.set()

with client:
    if connect_to:
        port.connect(connect_to)
    print('Playing', repr(filename), '... press Ctrl+C to stop')
    try:
        event.wait()
    except KeyboardInterrupt:

```

```
print('\nInterrupted by user')
```

3.8 Simple MIDI Synth

midi_sine.py

```
#!/usr/bin/env python3
"""Very basic MIDI synthesizer.

This only works in Python 3.x because it uses memoryview.cast() and a
few other sweet Python-3-only features.

This is inspired by the JACK example program "jack_midisine":
http://github.com/jackaudio/jack2/blob/master/example-clients/midisine.c

But it is actually better:

+ ASR envelope
+ unlimited polyphony (well, "only" limited by CPU and memory)
+ arbitrarily many MIDI events per block
+ can handle NoteOn and NoteOff event of the same pitch in one block

It is also worse:

- horribly inefficient (dynamic allocations, sample-wise processing)
- unpredictable because of garbage collection (?)

It sounds a little better than the original, but still quite boring.

"""
import jack
import math
import operator
import threading

# First 4 bits of status byte:
NOTEON = 0x9
NOTEOFF = 0x8

attack = 0.01 # seconds
release = 0.2 # seconds

fs = None
voices = {}

client = jack.Client('MIDI-Sine')
midiport = client.midi_inports.register('midi_in')
audioport = client.outports.register('audio_out')
event = threading.Event()

def m2f(note):
    """Convert MIDI note number to frequency in Hertz.

    See https://en.wikipedia.org/wiki/MIDI_Tuning_Standard.
```

(continues on next page)

```

"""
return 2 ** ((note - 69) / 12) * 440

class Voice:

    def __init__(self, pitch):
        self.time = 0
        self.time_increment = m2f(pitch) / fs
        self.weight = 0

        self.target_weight = 0
        self.weight_step = 0
        self.compare = None

    def trigger(self, vel):
        if vel:
            dur = attack * fs
        else:
            dur = release * fs
        self.target_weight = vel / 127
        self.weight_step = (self.target_weight - self.weight) / dur
        self.compare = operator.ge if self.weight_step > 0 else operator.le

    def update(self):
        """Increment weight."""
        if self.weight_step:
            self.weight += self.weight_step
            if self.compare(self.weight, self.target_weight):
                self.weight = self.target_weight
                self.weight_step = 0

@client.set_process_callback
def process(frames):
    """Main callback."""
    events = {}
    buf = memoryview(audioport.get_buffer()).cast('f')
    for offset, data in midiport.incoming_midi_events():
        if len(data) == 3:
            status, pitch, vel = bytes(data)
            # MIDI channel number is ignored!
            status >>= 4
            if status == NOTEON and vel > 0:
                events.setdefault(offset, []).append((pitch, vel))
            elif status in (NOTEON, NOTEOFF):
                # NoteOff velocity is ignored!
                events.setdefault(offset, []).append((pitch, 0))
            else:
                pass # ignore
        else:
            pass # ignore
    for i in range(len(buf)):
        buf[i] = 0
    try:

```

(continues on next page)


```

        eventlist = events[i]
    except KeyError:
        pass
    else:
        for pitch, vel in eventlist:
            if pitch not in voices:
                if not vel:
                    break
                voices[pitch] = Voice(pitch)
            voices[pitch].trigger(vel)
        for voice in voices.values():
            voice.update()
            if voice.weight > 0:
                buf[i] += voice.weight * math.sin(2 * math.pi * voice.time)
                voice.time += voice.time_increment
                if voice.time >= 1:
                    voice.time -= 1
dead = [k for k, v in voices.items() if v.weight <= 0]
for pitch in dead:
    del voices[pitch]

@client.set_samplerate_callback
def samplerate(samplerate):
    global fs
    fs = samplerate
    voices.clear()

@client.set_shutdown_callback
def shutdown(status, reason):
    print('JACK shutdown:', reason, status)
    event.set()

with client:
    print('Press Ctrl+C to stop')
    try:
        event.wait()
    except KeyboardInterrupt:
        print('\nInterrupted by user')

```

3.9 Simple MIDI Synth (NumPy Edition)

midi_sine_numpy.py

```

#!/usr/bin/env python3
"""Very basic MIDI synthesizer.

This does the same as midi_sine.py, but it uses NumPy and block
processing. It is therefore much more efficient. But there are still
many allocations and dynamically growing and shrinking data structures.

"""
import jack

```

(continues on next page)

```

import numpy as np
import threading

# First 4 bits of status byte:
NOTEON = 0x9
NOTEOFF = 0x8

attack_seconds = 0.01
release_seconds = 0.2

attack = None
release = None
fs = None
voices = {}

client = jack.Client('MIDI-Sine-NumPy')
midiport = client.midi_inports.register('midi_in')
audioport = client.outports.register('audio_out')
event = threading.Event()

def m2f(note):
    """Convert MIDI note number to frequency in Hertz.

    See https://en.wikipedia.org/wiki/MIDI_Tuning_Standard.

    """
    return 2 ** ((note - 69) / 12) * 440

def update_envelope(envelope, begin, target, vel):
    """Helper function to calculate envelopes.

    envelope: array of velocities, will be mutated
    begin: sample index where ramp begins
    target: sample index where *vel* shall be reached
    vel: final velocity value

    If the ramp goes beyond the blocksize, it is supposed to be
    continued in the next block.

    A reference to *envelope* is returned, as well as the (unchanged)
    *vel* and the target index of the following block where *vel* shall
    be reached.

    """
    blocksize = len(envelope)
    old_vel = envelope[begin]
    slope = (vel - old_vel) / (target - begin + 1)
    ramp = np.arange(min(target, blocksize) - begin) + 1
    envelope[begin:target] = ramp * slope + old_vel
    if target < blocksize:
        envelope[target:] = vel
        target = 0
    else:
        target -= blocksize

```

```

    return envelope, vel, target

@client.set_process_callback
def process(blocksize):
    """Main callback."""

    # Step 1: Update/delete existing voices from previous block

    # Iterating over a copy because items may be deleted:
    for pitch in list(voices):
        envelope, vel, target = voices[pitch]
        if any([vel, target]):
            envelope[0] = envelope[-1]
            voices[pitch] = update_envelope(envelope, 0, target, vel)
        else:
            del voices[pitch]

    # Step 2: Create envelopes from the MIDI events of the current block

    for offset, data in midiport.incoming_midi_events():
        if len(data) == 3:
            status, pitch, vel = bytes(data)
            # MIDI channel number is ignored!
            status >>= 4
            if status == NOTEON and vel > 0:
                try:
                    envelope, _, _ = voices[pitch]
                except KeyError:
                    envelope = np.zeros(blocksize)
                    voices[pitch] = update_envelope(
                        envelope, offset, offset + attack, vel)
            elif status in (NOTEON, NOTEOFF):
                # NoteOff velocity is ignored!
                try:
                    envelope, _, _ = voices[pitch]
                except KeyError:
                    print('NoteOff without NoteOn (ignored)')
                    continue
                voices[pitch] = update_envelope(
                    envelope, offset, offset + release, 0)
            else:
                pass # ignore
        else:
            pass # ignore

    # Step 3: Create sine tones, apply envelopes, add to output buffer

    buf = audioport.get_array()
    buf.fill(0)
    for pitch, (envelope, _, _) in voices.items():
        t = (np.arange(blocksize) + client.last_frame_time) / fs
        tone = np.sin(2 * np.pi * m2f(pitch) * t)
        buf += tone * envelope / 127

```

```

@client.set_samplerate_callback
def samplerate(samplerate):
    global fs, attack, release
    fs = samplerate
    attack = int(attack_seconds * fs)
    release = int(release_seconds * fs)
    voices.clear()

@client.set_shutdown_callback
def shutdown(status, reason):
    print('JACK shutdown:', reason, status)
    event.set()

with client:
    print('Press Ctrl+C to stop')
    try:
        event.wait()
    except KeyboardInterrupt:
        print('\nInterrupted by user')

```

4 API Documentation

JACK Client for Python.

<http://jackclient-python.readthedocs.io/>

jack.STOPPED = 0

Transport halted.

jack.ROLLING = 1

Transport playing.

jack.STARTING = 3

Waiting for sync ready.

jack.NETSTARTING = 4

Waiting for sync ready on the network.

jack.PROPERTY_CREATED = 0

A property was created. See *Client.set_property_change_callback()*.

jack.PROPERTY_CHANGED = 1

A property was changed. See *Client.set_property_change_callback()*.

jack.PROPERTY_DELETED = 2

A property was deleted. See *Client.set_property_change_callback()*.

jack.POSITION_BBT = 16

Bar, Beat, Tick.

jack.POSITION_TIMECODE = 32

External timecode.

jack.POSITION_BBT_FRAME_OFFSET = 64

Frame offset of BBT information.

`jack.POSITION_AUDIO_VIDEO_RATIO = 128`

Audio frames per video frame.

`jack.POSITION_VIDEO_FRAME_OFFSET = 256`

Frame offset of first video frame.

exception `jack.JackError`

Exception for all kinds of JACK-related errors.

exception `jack.JackErrorCode(message, code)`

Exception for JACK errors with an error code.

Subclass of *JackError*.

The following attributes are available:

message

Error message.

code

The error code returned by the JACK library function which resulted in this exception being raised.

exception `jack.JackOpenError(name, status)`

Exception raised for errors while creating a JACK client.

Subclass of *JackError*.

The following attributes are available:

name

Requested client name.

status

A *Status* instance representing the status information received by the `jack_client_open()` JACK library call.

class `jack.Client(name, use_exact_name=False, no_start_server=False, servername=None, session_id=None)`

Create a new JACK client.

A client object is a *context manager*, i.e. it can be used in a *with statement* to automatically call *activate()* in the beginning of the statement and *deactivate()* and *close()* on exit.

Parameters

name (*str*) – The desired client name of at most *client_name_size()* characters. The name scope is local to each server. Unless forbidden by the *use_exact_name* option, the server will modify this name to create a unique variant, if needed.

Other Parameters

- **use_exact_name** (*bool*) – Whether an error should be raised if *name* is not unique. See *Status.name_not_unique*.
- **no_start_server** (*bool*) – Do not automatically start the JACK server when it is not already running. This option is always selected if `JACK_NO_START_SERVER` is defined in the calling process environment.
- **servername** (*str*) – Selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use 'default' unless `JACK_DEFAULT_SERVER` is defined in the process environment.
- **session_id** (*str*) – Pass a SessionID Token. This allows the sessionmanager to identify the client again.

Raises

JackOpenError – If the session with the JACK server could not be opened.

property name

The name of the JACK client (read-only).

property uuid

The UUID of the JACK client (read-only).

Raises

JackError – If getting the UUID fails.

property samplerate

The sample rate of the JACK system (read-only).

property blocksize

The JACK block size (must be a power of two).

The current maximum size that will ever be passed to the process callback. It should only be queried *before* *activate()* has been called. This size may change, clients that depend on it must register a callback with *set_blocksize_callback()* so they will be notified if it does.

Changing the blocksize stops the JACK engine process cycle, then calls all registered callback functions (see *set_blocksize_callback()*) before restarting the process cycle. This will cause a gap in the audio flow, so it should only be done at appropriate stopping points.

property status

JACK client status. See *Status*.

property realtime

Whether JACK is running with *-R (--realtime)*.

property frames_since_cycle_start

Time since start of audio block.

The estimated time in frames that has passed since the JACK server began the current process cycle.

property frame_time

The estimated current time in frames.

This is intended for use in other threads (not the process callback). The return value can be compared with the value of *last_frame_time* to relate time in other threads to JACK time.

property last_frame_time

The precise time at the start of the current process cycle.

This may only be used from the process callback (see *set_process_callback()*), and can be used to interpret timestamps generated by *frame_time* in other threads with respect to the current process cycle.

This is the only jack time function that returns exact time: when used during the process callback it always returns the same value (until the next process callback, where it will return that value + *blocksize*, etc). The return value is guaranteed to be monotonic and linear in this fashion unless an xrun occurs (see *set_xrun_callback()*). If an xrun occurs, clients must check this value again, as time may have advanced in a non-linear way (e.g. cycles may have been skipped).

property inports

A list of audio input *Ports*.

New ports can be created and added to this list with *inports.register()*. When *unregister()* is called on one of the items in this list, this port is removed from the list. *inports.clear()* can be used to unregister all audio input ports at once.

See also:

Ports, *OwnPort*

property outports

A list of audio output *Ports*.

New ports can be created and added to this list with *outports.register()*. When *unregister()* is called on one of the items in this list, this port is removed from the list. *outports.clear()* can be used to unregister all audio output ports at once.

See also:

Ports, OwnPort

property midi_inports

A list of MIDI input *Ports*.

New MIDI ports can be created and added to this list with *midi_inports.register()*. When *unregister()* is called on one of the items in this list, this port is removed from the list. *midi_inports.clear()* can be used to unregister all MIDI input ports at once.

See also:

Ports, OwnMidiPort

property midi_outports

A list of MIDI output *Ports*.

New MIDI ports can be created and added to this list with *midi_outports.register()*. When *unregister()* is called on one of the items in this list, this port is removed from the list. *midi_outports.clear()* can be used to unregister all MIDI output ports at once.

See also:

Ports, OwnMidiPort

owns(port)

Check if a given port belongs to *self*.

Parameters

port (*str or Port*) – Full port name or *Port, MidiPort, OwnPort* or *OwnMidiPort* object.

activate()

Activate JACK client.

Tell the JACK server that the program is ready to start processing audio.

deactivate(ignore_errors=True)

De-activate JACK client.

Tell the JACK server to remove *self* from the process graph. Also, disconnect all ports belonging to it, since inactive clients have no port connections.

cpu_load()

Return the current CPU load estimated by JACK.

This is a running average of the time it takes to execute a full process cycle for all clients as a percentage of the real time available per cycle determined by *blocksize* and *samplerate*.

close(ignore_errors=True)

Close the JACK client.

connect(source, destination)

Establish a connection between two ports.

When a connection exists, data written to the source port will be available to be read at the destination port.

Audio ports can obviously not be connected with MIDI ports.

Parameters

- **source** (*str or Port*) – One end of the connection. Must be an output port.
- **destination** (*str or Port*) – The other end of the connection. Must be an input port.

See also:

[*OwnPort.connect, disconnect*](#)

Raises

JackError – If there is already an existing connection between *source* and *destination* or the connection can not be established.

disconnect(*source, destination*)

Remove a connection between two ports.

Parameters

source, destination (*str or Port*) – See [*connect\(\)*](#).

transport_start()

Start JACK transport.

transport_stop()

Stop JACK transport.

property transport_state

JACK transport state.

This is one of [*STOPPED*](#), [*ROLLING*](#), [*STARTING*](#), [*NETSTARTING*](#).

See also:

[*transport_query*](#)

property transport_frame

Get/set current JACK transport frame.

Return an estimate of the current transport frame, including any time elapsed since the last transport positional update. Assigning a frame number repositions the JACK transport.

transport_locate(*frame*)

Deprecated since version 0.4.1: Use [*transport_frame*](#) instead

transport_query()

Query the current transport state and position.

This is a convenience function that does the same as [*transport_query_struct\(\)*](#), but it only returns the valid fields in an easy-to-use dict.

Returns

- **state** (*TransportState*) – The transport state can take following values: [*STOPPED*](#), [*ROLLING*](#), [*STARTING*](#) and [*NETSTARTING*](#).
- **position** (*dict*) – A dictionary containing only the valid fields of the structure returned by [*transport_query_struct\(\)*](#).

See also:

[*transport_state, transport_query_struct*](#)

transport_query_struct()

Query the current transport state and position.

This function is realtime-safe, and can be called from any thread. If called from the process thread, the returned position corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

Returns

- **state** (*int*) – The transport state can take following values: [STOPPED](#), [ROLLING](#), [STARTING](#) and [NETSTARTING](#).
- **position** (*jack_position_t*) – See the [JACK transport documentation](#)¹² for the available fields.

See also:

[transport_query](#), [transport_reposition_struct](#)

transport_reposition_struct(*position*)

Request a new transport position.

May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the [STARTING](#) state and begin invoking their sync callbacks (see [set_sync_callback\(\)](#)) until ready. This function is realtime-safe.

Parameters

position (*jack_position_t*) – Requested new transport position. This is the same structure as returned by [transport_query_struct\(\)](#).

See also:

[transport_query_struct](#), [transport_locate](#)

set_sync_timeout(*timeout*)

Set the timeout value for slow-sync clients.

This timeout prevents unresponsive slow-sync clients from completely halting the transport mechanism. The default is two seconds. When the timeout expires, the transport starts rolling, even if some slow-sync clients are still unready. The *sync callbacks* of these clients continue being invoked, giving them a chance to catch up.

Parameters

timeout (*int*) – Delay (in microseconds) before the timeout expires.

See also:

[set_sync_callback](#)

set_freewheel(*onoff*)

Start/Stop JACK's "freewheel" mode.

When in "freewheel" mode, JACK no longer waits for any external event to begin the start of the next process cycle.

As a result, freewheel mode causes "faster than realtime" execution of a JACK graph. If possessed, real-time scheduling is dropped when entering freewheel mode, and if appropriate it is reacquired when stopping.

IMPORTANT: on systems using capabilities to provide real-time scheduling (i.e. Linux kernel 2.4), if onoff is zero, this function must be called from the thread that originally called [activate\(\)](#). This restriction does not apply to other systems (e.g. Linux kernel 2.6 or OS X).

Parameters

onoff (*bool*) – If True, freewheel mode starts. Otherwise freewheel mode ends.

See also:

[set_freewheel_callback](#)

set_shutdown_callback(*callback*)

Register shutdown callback.

Register a function (and optional argument) to be called if and when the JACK server shuts down the client thread. The function must be written as if it were an asynchronous POSIX signal handler – use only async-safe functions, and remember that it is executed from another thread. A typical function

might set a flag or write to a pipe so that the rest of the application knows that the JACK client thread has shut down.

Note: Clients do not need to call this. It exists only to help more complex clients understand what is going on. It should be called before `activate()`.

Parameters

callback (*callable*) – User-supplied function that is called whenever the JACK daemon is shutdown. It must have this signature:

```
callback(status: Status, reason: str) -> None
```

The argument *status* is of type `jack.Status`.

Note: The *callback* should typically signal another thread to correctly finish cleanup by calling `close()` (since it cannot be called directly in the context of the thread that calls the shutdown callback).

After server shutdown, the client is *not* deallocated by JACK, the user (that's you!) is responsible to properly use `close()` to release client resources. Alternatively, the `Client` object can be used as a *context manager* in a *with statement*, which takes care of activating, deactivating and closing the client automatically.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

`set_process_callback(callback)`

Register process callback.

Tell the JACK server to call *callback* whenever there is work be done.

The code in the supplied function must be suitable for real-time execution. That means that it cannot call functions that might block for a long time. This includes `malloc`, `free`, `printf`, `pthread_mutex_lock`, `sleep`, `wait`, `poll`, `select`, `pthread_join`, `pthread_cond_wait`, etc, etc.

Warning: Most Python interpreters use a [global interpreter lock \(GIL\)](#)¹³, which violates the above real-time requirement. Furthermore, Python's [garbage collector](#)¹⁴ might become active at an inconvenient time and block the process callback for some time.

Because of this, Python is not really suitable for real-time processing. If you want to implement a *reliable* real-time audio/MIDI application, you should use a different programming language, such as C or C++.

If you can live with some random audio drop-outs now and then, feel free to continue using Python!

Note: This function cannot be called while the client is activated (after `activate()` has been called).

Parameters

callback (*callable*) – User-supplied function that is called by the engine anytime there is work to be done. It must have this signature:

```
callback(frames: int) -> None
```

The argument *frames* specifies the number of frames that have to be processed in the current audio block. It will be the same number as *blocksize* and it will be a power of two.

As long as the client is active, the *callback* will be called once in each process cycle. However, if an exception is raised inside of a *callback*, it will not be called anymore. The exception *CallbackExit* can be used to silently prevent further callback invocations, all other exceptions will print an error message to *stderr*.

set_freewheel_callback(*callback*)

Register freewheel callback.

Tell the JACK server to call *callback* whenever we enter or leave “freewheel” mode. The argument to the callback will be **True** if JACK is entering freewheel mode, and **False** otherwise.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after *activate()* has been called).

Parameters

callback (*callable*) – User-supplied function that is called whenever JACK starts or stops freewheeling. It must have this signature:

```
callback(starting: bool) -> None
```

The argument *starting* is **True** if we start to freewheel, **False** otherwise.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

See also:

[*set_freewheel*](#)

set_blocksize_callback(*callback*)

Register blocksize callback.

Tell JACK to call *callback* whenever the size of the the buffer that will be passed to the process callback is about to change. Clients that depend on knowing the buffer size must supply a *callback* before activating themselves.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after *activate()* has been called).

Parameters

callback (*callable*) – User-supplied function that is invoked whenever the JACK engine buffer size changes. It must have this signature:

```
callback(blocksize: int) -> None
```

The argument *blocksize* is the new buffer size. The *callback* is supposed to raise *CallbackExit* on error.

Note: Although this function is called in the JACK process thread, the normal process cycle is suspended during its operation, causing a gap in the audio flow. So, the *callback* can allocate storage, touch memory not previously referenced, and perform other operations that are not realtime safe.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

See also:

[*blocksize*](#)

set_samplerate_callback(*callback*)

Register samplerate callback.

Tell the JACK server to call *callback* whenever the system sample rate changes.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after [*activate\(\)*](#) has been called).

Parameters

callback (*callable*) – User-supplied function that is called when the engine sample rate changes. It must have this signature:

```
callback(samplerate: int) -> None
```

The argument *samplerate* is the new engine sample rate. The *callback* is supposed to raise [*CallbackExit*](#) on error.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

See also:

[*samplerate*](#)

set_client_registration_callback(*callback*)

Register client registration callback.

Tell the JACK server to call *callback* whenever a client is registered or unregistered.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after [*activate\(\)*](#) has been called).

Parameters

callback (*callable*) – User-supplied function that is called whenever a client is registered or unregistered. It must have this signature:

```
callback(name: str, register: bool) -> None
```

The first argument contains the client name, the second argument is `True` if the client is being registered and `False` if the client is being unregistered.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

set_port_registration_callback(*callback=None, only_available=True*)

Register port registration callback.

Tell the JACK server to call *callback* whenever a port is registered or unregistered.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after `activate()` has been called).

Note: Due to JACK 1 behavior, it is not possible to get the pointer to an unregistering JACK Port if it already existed before `activate()` was called. This will cause the callback not to be called if *only_available* is `True`, or called with `None` as first argument (see below).

To avoid this, call `Client.get_ports()` just after `activate()`, allowing the module to store pointers to already existing ports and always receive a `Port` argument for this callback.

Parameters

- **callback** (*callable*) – User-supplied function that is called whenever a port is registered or unregistered. It must have this signature:

`callback(port: Port, register: bool) -> None`

The first argument is a `Port`, `MidiPort`, `OwnPort` or `OwnMidiPort` object, the second argument is `True` if the port is being registered, `False` if the port is being unregistered.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

- **only_available** (*bool, optional*) – If `True`, the *callback* is not called if the port in question is not available anymore (after another JACK client has unregistered it). If `False`, it is called nonetheless, but the first argument of the *callback* will be `None` if the port is not available anymore.

See also:

`Ports.register`

set_port_connect_callback(*callback=None, only_available=True*)

Register port connect callback.

Tell the JACK server to call *callback* whenever a port is connected or disconnected.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after `activate()` has been called).

Note: Due to JACK 1 behavior, it is not possible to get the pointer to an unregistering JACK Port if it already existed before `activate()` was called. This will cause the callback not to be called if `only_available` is `True`, or called with `None` as first argument (see below).

To avoid this, call `Client.get_ports()` just after `activate()`, allowing the module to store pointers to already existing ports and always receive a `Port` argument for this callback.

Parameters

- **callback** (*callable*) – User-supplied function that is called whenever a port is connected or disconnected. It must have this signature:

```
callback(a: Port, b: Port, connect: bool) -> None
```

The first and second arguments contain `Port`, `MidiPort`, `OwnPort` or `OwnMidiPort` objects of the ports which are connected or disconnected. The third argument is `True` if the ports were connected and `False` if the ports were disconnected.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

- **only_available** (*bool, optional*) – See `set_port_registration_callback()`. If `False`, the first and/or the second argument to the *callback* may be `None`.

See also:

`Client.connect`, `OwnPort.connect`

set_port_rename_callback(*callback=None, only_available=True*)

Register port rename callback.

Tell the JACK server to call *callback* whenever a port is renamed.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after `activate()` has been called).

Parameters

- **callback** (*callable*) – User-supplied function that is called whenever the port name has been changed. It must have this signature:

```
callback(port: Port, old: str, new: str) -> None
```

The first argument is the port that has been renamed (a `Port`, `MidiPort`, `OwnPort` or `OwnMidiPort` object); the second and third argument is the old and new name, respectively. The *callback* is supposed to raise `CallbackExit` on error.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

- **only_available** (*bool, optional*) – See `set_port_registration_callback()`.

See also:

`Port.shortname`

Notes

The port rename callback is not available in JACK 1! See and [this commit message](#)¹⁵.

set_graph_order_callback(*callback*)

Register graph order callback.

Tell the JACK server to call *callback* whenever the processing graph is reordered.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after [activate\(\)](#) has been called).

Parameters

callback (*callable*) – User-supplied function that is called whenever the processing graph is reordered. It must have this signature:

<code>callback() -> None</code>

The *callback* is supposed to raise [CallbackExit](#) on error.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

set_xrun_callback(*callback*)

Register xrun callback.

Tell the JACK server to call *callback* whenever there is an xrun.

All “notification events” are received in a separated non RT thread, the code in the supplied function does not need to be suitable for real-time execution.

Note: This function cannot be called while the client is activated (after [activate\(\)](#) has been called).

Parameters

callback (*callable*) – User-supplied function that is called whenever an xrun has occurred. It must have this signature:

<code>callback(delayed_usecs: float) -> None</code>
--

The callback argument is the delay in microseconds due to the most recent XRUN occurrence. The *callback* is supposed to raise [CallbackExit](#) on error.

Note: Same as with most callbacks, no functions that interact with the JACK daemon should be used here.

set_sync_callback(*callback*)

Register (or unregister) as a slow-sync client.

A slow-sync client is one that cannot respond immediately to transport position changes.

The *callback* will be invoked at the first available opportunity after its registration is complete. If the client is currently active this will be the following process cycle, otherwise it will be the first cycle after calling [activate\(\)](#). After that, it runs whenever some client requests a new position, or the transport

enters the *STARTING* state. While the client is active, this callback is invoked just before the *process callback* (see *set_process_callback()*) in the same thread.

Clients that don't set a *sync callback* are assumed to be ready immediately any time the transport wants to start.

Parameters

callback (*callable or None*) – User-supplied function that returns True when the slow-sync client is ready. This realtime function must not wait. It must have this signature:

```
callback(state: int, pos: jack_position_t) -> bool
```

The *state* argument will be:

- *STOPPED* when a new position is requested;
- *STARTING* when the transport is waiting to start;
- *ROLLING* when the timeout has expired, and the position is now a moving target.

The *pos* argument holds the new transport position using the same structure as returned by *transport_query_struct()*.

Setting *callback* to None declares that this client no longer requires slow-sync processing.

See also:

set_sync_timeout

release_timebase()

De-register as timebase master.

Should be called by the current timebase master to release itself from that responsibility and to stop the callback registered with *set_timebase_callback()* from being called.

If the timebase master releases the timebase or leaves the JACK graph for any reason, the JACK engine takes over at the start of the next process cycle. The transport state does not change. If rolling, it continues to play, with frame numbers as the only available position information.

Raises

JackError – If the client is not the current timebase master or releasing the timebase failed for another reason

See also:

set_timebase_callback

set_timebase_callback(callback=None, conditional=False)

Register as timebase master for the JACK subsystem.

The timebase master registers a callback that updates extended position information such as beats or timecode whenever necessary. Without this extended information, there is no need for this function.

There is never more than one master at a time. When a new client takes over, the former callback is no longer called. Taking over the timebase may be done conditionally, so that *callback* is not registered if there was a master already.

Parameters

- **callback** (*callable*) – Realtime function that returns extended position information. Its output affects all of the following process cycle. This realtime function must not wait. It is called immediately after the process callback (see *set_process_callback()*) in the same thread whenever the transport is rolling, or when any client has requested a new position in the previous cycle. The first cycle after *set_timebase_callback()* is also treated as a new position, or the first cycle after *activate()* if the client had been inactive. The *callback* must have this signature:


```
callback(
    state: int,
    blocksize: int,
    pos: jack_position_t,
    new_pos: bool,
) -> None
```

state

The current transport state. See [transport_state](#).

blocksize

The number of frames in the current period. See [blocksize](#).

pos

The position structure for the next cycle; `pos.frame` will be its frame number. If `new_pos` is `False`, this structure contains extended position information from the current cycle. If `new_pos` is `True`, it contains whatever was set by the requester. The `callback`'s task is to update the extended information here. See [transport_query_struct\(\)](#) for details about `jack_position_t`.

new_pos

`True` for a newly requested `pos`, or for the first cycle after the timebase callback is defined.

Note: The `pos` argument must not be used to set `pos.frame`. To change position, use [transport_reposition_struct\(\)](#) or [transport_locate\(\)](#). These functions are realtime-safe, the timebase callback can call them directly.

- **conditional** (*bool*) – Set to `True` for a conditional request.

Returns

bool – `True` if the timebase callback was registered. `False` if a conditional request failed because another timebase master is already registered.

set_property_change_callback(callback)

Register property change callback.

Tell the JACK server to call `callback` whenever a property is created, changed or deleted.

Parameters

callback (*callable*) – User-supplied function that is called whenever a property is created, changed or deleted. It must have this signature:

```
callback(subject: int, key: str, change: int) -> None
```

The first and second arguments are the *subject* and *key*, respectively. See [set_property\(\)](#) for details. The third argument has one of the values [PROPERTY_CREATED](#), [PROPERTY_CHANGED](#) or [PROPERTY_DELETED](#), which should be self-explanatory.

get_uuid_for_client_name(name)

Get the session ID for a client name.

The session manager needs this to reassociate a client name to the session ID.

Raises

JackError – If no client with the given name exists.

get_client_name_by_uuid(*uuid*)

Get the client name for a session ID.

In order to snapshot the graph connections, the session manager needs to map session IDs to client names.

Raises

JackError – If no client with the given UUID exists.

get_port_by_name(*name*)

Get port by name.

Given a full port name, this returns a *Port*, *MidiPort*, *OwnPort* or *OwnMidiPort* object.

Raises

JackError – If no port with the given name exists.

get_all_connections(*port*)

Return a list of ports which the given port is connected to.

This differs from *OwnPort.connections* (also available on *OwnMidiPort*) in two important respects:

- 1) You may not call this function from code that is executed in response to a JACK event. For example, you cannot use it in a graph order callback.
- 2) You need not be the owner of the port to get information about its connections.

get_ports(*name_pattern=""*, *is_audio=False*, *is_midi=False*, *is_input=False*, *is_output=False*, *is_physical=False*, *can_monitor=False*, *is_terminal=False*)

Return a list of selected ports.

Parameters

- **name_pattern** (*str*) – A regular expression used to select ports by name. If empty, no selection based on name will be carried out.
- **is_audio**, **is_midi** (*bool*) – Select audio/MIDI ports. If neither of them is *True*, both types of ports are selected.
- **is_input**, **is_output**, **is_physical**, **can_monitor**, **is_terminal** (*bool*) – Select ports by their flags. If none of them are *True*, no selection based on flags will be carried out.

Returns

list of Port/MidiPort/OwnPort/OwnMidiPort – All ports that satisfy the given conditions.

set_property(*subject*, *key*, *value*, *type=""*)

Set a metadata property on *subject*.

Parameters

- **subject** (*int or str*) – The subject (UUID) to set the property on. UUIDs can be obtained with *Client.uuid*, *Port.uuid* and *Client.get_uuid_for_client_name()*.
- **key** (*str*) – The key (URI) of the property. Some predefined keys are available as *jack.METADATA_** module constants.
- **value** (*str or bytes*) – The value of the property.
- **type** (*str, optional*) – The type of the property, either a MIME type or URI. If *type* is empty, the *value* is assumed to be a UTF-8 encoded string ('*text/plain*').

Example values:

- '*image/png;base64*' (base64 encoded PNG image)
- '*http://www.w3.org/2001/XMLSchema#int*' (integer)

Official types are preferred, but clients may use any syntactically valid MIME type (which start with a type and slash, like '*text/...*'). If a URI type is used, it must be a complete absolute URI (which start with a scheme and colon, like '*http:*').

See also:

[`get_property`](#), [`get_properties`](#), [`get_all_properties`](#), [`remove_property`](#),
[`remove_properties`](#), [`remove_all_properties`](#), [`set_property_change_callback`](#)

remove_property(*subject*, *key*)

Remove a single metadata property on *subject*.

Parameters

- **subject** (*int or str*) – The subject (UUID) to remove the property from. UUIDs can be obtained with [`Client.uuid`](#), [`Port.uuid`](#) and [`Client.get_uuid_for_client_name\(\)`](#).
- **key** (*str*) – The key of the property to be removed.

See also:

[`set_property`](#), [`get_property`](#), [`get_properties`](#), [`get_all_properties`](#), [`remove_properties`](#),
[`remove_all_properties`](#), [`set_property_change_callback`](#)

remove_properties(*subject*)

Remove all metadata properties on *subject*.

Parameters

subject (*int or str*) – The subject (UUID) to remove all properties from. UUIDs can be obtained with [`Client.uuid`](#), [`Port.uuid`](#) and [`Client.get_uuid_for_client_name\(\)`](#).

Returns

int – The number of properties removed.

See also:

[`set_property`](#), [`get_property`](#), [`get_properties`](#), [`get_all_properties`](#), [`remove_property`](#),
[`remove_all_properties`](#), [`set_property_change_callback`](#)

remove_all_properties()

Remove all metadata properties.

Warning: This deletes all metadata managed by a running JACK server. Data lost cannot be recovered (though it can be recreated by new calls to [`set_property\(\)`](#)).

See also:

[`set_property`](#), [`get_property`](#), [`get_properties`](#), [`get_all_properties`](#), [`remove_property`](#),
[`remove_properties`](#), [`set_property_change_callback`](#)

class `jack.Port`(*port_ptr*, *client*)

A JACK audio port.

This class cannot be instantiated directly. Instead, instances of this class are returned from [`Client.get_port_by_name\(\)`](#), [`Client.get_ports\(\)`](#), [`Client.get_all_connections\(\)`](#) and [`OwnPort.connections`](#). In addition, instances of this class are available in the callbacks which are set with [`Client.set_port_registration_callback\(\)`](#), [`Client.set_port_connect_callback\(\)`](#) or [`Client.set_port_rename_callback\(\)`](#).

Note, however, that if the used [`Client`](#) owns the respective port, instances of [`OwnPort`](#) (instead of [`Port`](#)) will be created. In case of MIDI ports, instances of [`MidiPort`](#) or [`OwnMidiPort`](#) are created.

Besides being the type of non-owned JACK audio ports, this class also serves as base class for all other port classes ([`OwnPort`](#), [`MidiPort`](#) and [`OwnMidiPort`](#)).

¹² https://jackaudio.org/api/structjack__position__t.html

¹³ https://en.wikipedia.org/wiki/Global_Interpreter_Lock

¹⁴ [https://en.wikipedia.org/wiki/Garbage_collection_\(computer_science\)](https://en.wikipedia.org/wiki/Garbage_collection_(computer_science))

¹⁵ <https://github.com/jackaudio/jack1/commit/94c819accfab2612050e875c24cf325daa0fd26d>

New JACK audio/MIDI ports can be created with the `register()` method of `Client.inports`, `Client.outports`, `Client.midi_inports` and `Client.midi_outports`.

property name

Full name of the JACK port (read-only).

property shortname

Short name of the JACK port, not including the client name.

Must be unique among all ports owned by a client.

May be modified at any time. If the resulting full name (including the `client_name:` prefix) is longer than `port_name_size()`, it will be truncated.

property aliases

Returns a list of strings with the aliases for the JACK port.

set_alias(alias)

Set an alias for the JACK port.

Ports can have up to two aliases. If both are already set, this function will return an error.

unset_alias(alias)

Remove an alias for the JACK port.

If the alias doesn't exist this function will return an error.

property uuid

The UUID of the JACK port.

property is_audio

This is always True.

property is_midi

This is always False.

property is_input

Can the port receive data?

property is_output

Can data be read from this port?

property is_physical

Does it correspond to some kind of physical I/O connector?

property can_monitor

Does a call to `request_monitor()` make sense?

property is_terminal

Is the data consumed/generated?

request_monitor(onoff)

Set input monitoring.

If `can_monitor` is True, turn input monitoring on or off. Otherwise, do nothing.

Parameters

onoff (*bool*) – If True, switch monitoring on; if False, switch it off.

class jack.MidiPort(port_ptr, client)

A JACK MIDI port.

This class is derived from `Port` and has exactly the same attributes and methods.

This class cannot be instantiated directly (see `Port`).

New JACK audio/MIDI ports can be created with the `register()` method of `Client.inports`, `Client.outports`, `Client.midi_inports` and `Client.midi_outports`.

See also:

`Port`, `OwnMidiPort`

property is_audio

This is always False.

property is_midi

This is always True.

class `jack.OwnPort(port_ptr, client)`

A JACK audio port owned by a `Client`.

This class is derived from `Port`. `OwnPort` objects can do everything that `Port` objects can, plus a lot more.

This class cannot be instantiated directly (see `Port`).

New JACK audio/MIDI ports can be created with the `register()` method of `Client.inports`, `Client.outports`, `Client.midi_inports` and `Client.midi_outports`.

property number_of_connections

Number of connections to or from port.

property connections

List of ports which the port is connected to.

is_connected_to(port)

Am I *directly* connected to *port*?

Parameters

port (*str or Port*) – Full port name or port object.

connect(port)

Connect to given port.

Parameters

port (*str or Port*) – Full port name or port object.

See also:

`Client.connect`

disconnect(other=None)

Disconnect this port.

Parameters

other (*str or Port*) – Port to disconnect from. By default, disconnect from all connected ports.

unregister()

Unregister port.

Remove the port from the client, disconnecting any existing connections. This also removes the port from `Client.inports`, `Client.outports`, `Client.midi_inports` or `Client.midi_outports`.

get_buffer()

Get buffer for audio data.

This returns a buffer holding the memory area associated with the specified port. For an output port, it will be a memory area that can be written to; for an input port, it will be an area containing the data from the port's connection(s), or zero-filled. If there are multiple inbound connections, the data will be mixed appropriately.

Caching output ports is DEPRECATED in JACK 2.0, due to some new optimization (like “pipelining”). Port buffers have to be retrieved in each callback for proper functioning.

This method shall only be called from within the process callback (see [Client.set_process_callback\(\)](#)).

get_array()

Get audio buffer as NumPy array.

Make sure to `import numpy` before calling this, otherwise the first call might take a long time.

This method shall only be called from within the process callback (see [Client.set_process_callback\(\)](#)).

See also:

[get_buffer](#)

class `jack.OwnMidiPort(*args, **kwargs)`

A JACK MIDI port owned by a [Client](#).

This class is derived from [OwnPort](#) and [MidiPort](#), which are themselves derived from [Port](#). It has the same attributes and methods as [OwnPort](#), but [get_buffer\(\)](#) and [get_array\(\)](#) are disabled. Instead, it has methods for sending and receiving MIDI events (to be used only from within the process callback – see [Client.set_process_callback\(\)](#)).

This class cannot be instantiated directly (see [Port](#)).

New JACK audio/MIDI ports can be created with the [register\(\)](#) method of [Client.inports](#), [Client.outports](#), [Client.midi_inports](#) and [Client.midi_outports](#).

get_buffer()

Not available for MIDI ports.

get_array()

Not available for MIDI ports.

property max_event_size

Get the size of the largest event that can be stored by the port.

This returns the current space available, taking into account events already stored in the port.

property lost_midi_events

Get the number of events that could not be written to the port.

This being a non-zero value implies that the port is full. Currently the only way this can happen is if events are lost on port mixdown.

incoming_midi_events()

Return generator for incoming MIDI events.

JACK MIDI is normalised, the MIDI events yielded by this generator are guaranteed to be complete MIDI events (the status byte will always be present, and no realtime events will be interspersed with the events).

Yields

- **time** (*int*) – Time (in samples) relative to the beginning of the current audio block.
- **event** (*buffer*) – The actual MIDI event data.

Warning: The buffer is re-used (and therefore overwritten) between iterations. If you want to keep the data beyond the current iteration, please make a copy.

clear_buffer()

Clear an event buffer.

This should be called at the beginning of each process cycle before calling `reserve_midi_event()` or `write_midi_event()`. This function may not be called on an input port.

write_midi_event(time, event)

Create an outgoing MIDI event.

Clients must write normalised MIDI data to the port - no running status and no (one-byte) realtime messages interspersed with other messages (realtime messages are fine when they occur on their own, like other messages).

Events must be written in order, sorted by their sample offsets. JACK will not sort the events for you, and will refuse to store out-of-order events.

Parameters

- **time** (*int*) – Time (in samples) relative to the beginning of the current audio block.
- **event** (*bytes or buffer or sequence of int*) – The actual MIDI event data.

Note: Buffer objects are only supported for CFFI >= 0.9.

Raises

JackError – If MIDI event couldn't be written.

reserve_midi_event(time, size)

Get a buffer where an outgoing MIDI event can be written to.

Clients must write normalised MIDI data to the port - no running status and no (one-byte) realtime messages interspersed with other messages (realtime messages are fine when they occur on their own, like other messages).

Events must be written in order, sorted by their sample offsets. JACK will not sort the events for you, and will refuse to store out-of-order events.

Parameters

- **time** (*int*) – Time (in samples) relative to the beginning of the current audio block.
- **size** (*int*) – Number of bytes to reserve.

Returns

buffer – A buffer object where MIDI data bytes can be written to. If no space could be reserved, an empty buffer is returned.

class jack.Ports(client, porttype, flag)

A list of input/output ports.

This class is not meant to be instantiated directly. It is only used as `Client.inports`, `Client.outports`, `Client.midi_inports` and `Client.midi_outports`.

The ports can be accessed by indexing or by iteration.

New ports can be added with `register()`, existing ports can be removed by calling their `unregister()` method.

register(shortname, is_terminal=False, is_physical=False)

Create a new input/output port.

The new `OwnPort` or `OwnMidiPort` object is automatically added to `Client.inports`, `Client.outports`, `Client.midi_inports` or `Client.midi_outports`.

Parameters

- **shortname** (*str*) – Each port has a short name. The port’s full name contains the name of the client concatenated with a colon (:) followed by its short name. The `port_name_size()` is the maximum length of this full name. Exceeding that will cause the port registration to fail.

The port name must be unique among all ports owned by this client. If the name is not unique, the registration will fail.

- **is_terminal** (*bool*) – For an input port: If True, the data received by the port will not be passed on or made available at any other port. For an output port: If True, the data available at the port does not originate from any other port

Audio synthesizers, I/O hardware interface clients, HDR systems are examples of clients that would set this flag for their ports.

- **is_physical** (*bool*) – If True the port corresponds to some kind of physical I/O connector.

Returns

Port – A new `OwnPort` or `OwnMidiPort` instance.

`clear()`

Unregister all ports in the list.

See also:

`OwnPort.unregister`

`class jack.RingBuffer(size)`

Create a lock-free ringbuffer.

A ringbuffer is a good way to pass data between threads (e.g. between the main program and the process callback), when streaming realtime data to slower media, like audio file playback or recording.

The key attribute of a ringbuffer is that it can be safely accessed by two threads simultaneously – one reading from the buffer and the other writing to it – without using any synchronization or mutual exclusion primitives. For this to work correctly, there can only be a single reader and a single writer thread. Their identities cannot be interchanged.

Parameters

size (*int*) – Size in bytes. JACK will allocate a buffer of at least this size (rounded up to the next power of 2), but one byte is reserved for internal use. Use `write_space` to determine the actual size available for writing.

Raises

`JackError` – If the ringbuffer could not be allocated.

property `write_space`

The number of bytes available for writing.

`write(data)`

Write data into the ringbuffer.

Parameters

data (*buffer or bytes or iterable of int*) – Bytes to be written to the ringbuffer.

Returns

int – The number of bytes written, which could be less than the length of *data* if there was no more space left (see `write_space`).

See also:

`write_space`, `write_buffers`

property `write_buffers`

Contains two buffer objects that can be written to directly.

Two are needed because the space available for writing may be split across the end of the ringbuffer. Either of them could be 0 length.

This can be used as a no-copy version of `write()`.

When finished with writing, `write_advance()` should be used.

Note: After an operation that changes the write pointer (`write()`, `write_advance()`, `reset()`), the buffers are no longer valid and one should use this property again to get new ones.

`write_advance(size)`

Advance the write pointer.

After data has been written to the ringbuffer using `write_buffers`, use this method to advance the buffer pointer, making the data available for future read operations.

Parameters

size (*int*) – The number of bytes to advance.

property `read_space`

The number of bytes available for reading.

`read(size)`

Read data from the ringbuffer.

Parameters

size (*int*) – Number of bytes to read.

Returns

buffer – A buffer object containing the requested data. If no more data is left (see `read_space`), a smaller (or even empty) buffer is returned.

See also:

`peek`, `read_space`, `read_buffers`

`peek(size)`

Peek at data from the ringbuffer.

Opposed to `read()` this function does not move the read pointer. Thus it's a convenient way to inspect data in the ringbuffer in a continuous fashion. The price is that the data is copied into a newly allocated buffer. For "raw" non-copy inspection of the data in the ringbuffer use `read_buffers`.

Parameters

size (*int*) – Number of bytes to peek.

Returns

buffer – A buffer object containing the requested data. If no more data is left (see `read_space`), a smaller (or even empty) buffer is returned.

See also:

`read`, `read_space`, `read_buffers`

property `read_buffers`

Contains two buffer objects that can be read directly.

Two are needed because the data to be read may be split across the end of the ringbuffer. Either of them could be 0 length.

This can be used as a no-copy version of `peek()` or `read()`.

When finished with reading, `read_advance()` should be used.

Note: After an operation that changes the read pointer ([read\(\)](#), [read_advance\(\)](#), [reset\(\)](#)), the buffers are no longer valid and one should use this property again to get new ones.

read_advance(*size*)

Advance the read pointer.

After data has been read from the ringbuffer using [read_buffers](#) or [peek\(\)](#), use this method to advance the buffer pointers, making that space available for future write operations.

Parameters

size (*int*) – The number of bytes to advance.

mlock()

Lock a ringbuffer data block into memory.

Uses the `mlock()` system call. This prevents the ringbuffer's memory from being paged to the swap area.

Note: This is not a realtime operation.

reset(*size=None*)

Reset the read and write pointers, making an empty buffer.

Note: This is not thread safe.

Parameters

size (*int, optional*) – The new size for the ringbuffer. Must be less than allocated size.

property size

The number of bytes in total used by the buffer.

See also:

[read_space](#), [write_space](#)

class jack.Status(*code*)

Representation of the JACK status bits.

property failure

Overall operation failed.

property invalid_option

The operation contained an invalid or unsupported option.

property name_not_unique

The desired client name was not unique.

With the `use_exact_name` option of [Client](#), this situation is fatal. Otherwise, the name is modified by appending a dash and a two-digit number in the range “-01” to “-99”. [Client.name](#) will return the exact string that was used. If the specified *name* plus these extra characters would be too long, the open fails instead.

property server_started

The JACK server was started for this [Client](#).

Otherwise, it was running already.

property server_failed

Unable to connect to the JACK server.

property server_error

Communication error with the JACK server.

property no_such_client

Requested client does not exist.

property load_failure

Unable to load internal client.

property init_failure

Unable to initialize client.

property shm_failure

Unable to access shared memory.

property version_error

Client's protocol version does not match.

property backend_error

Backend error.

property client_zombie

Client zombified failure.

class jack.TransportState(*code*)

Representation of the JACK transport state.

See also:

None, [*Client.transport_query\(\)*](#)

exception jack.CallbackExit

To be raised in a callback function to signal failure.

See also:

[*Client.set_process_callback\(\)*](#), [*Client.set_blocksize_callback\(\)*](#), [*Client.set_samplerate_callback\(\)*](#), [*Client.set_port_rename_callback\(\)*](#), [*Client.set_graph_order_callback\(\)*](#), [*Client.set_xrun_callback\(\)*](#)

jack.get_property(*subject*, *key*)

Get a metadata property on *subject*.

Parameters

- **subject** (*int* or *str*) – The subject (UUID) to get the property from. UUIDs can be obtained with [*Client.uuid*](#), [*Port.uuid*](#) and [*Client.get_uuid_for_client_name\(\)*](#).
- **key** (*str*) – The key of the property.

Returns

(*bytes*, *str*) or *None* – A tuple containing the value of the property and the type of the property. If *subject* doesn't have the property *key*, *None* is returned.

See also:

[*Client.set_property*](#), [*get_properties*](#), [*get_all_properties*](#), [*Client.remove_property*](#), [*Client.remove_properties*](#), [*Client.remove_all_properties*](#), [*Client.set_property_change_callback*](#)

jack.get_properties(subject)

Get all metadata properties of *subject*.

Parameters

subject (*int or str*) – The subject (UUID) to get all properties of. UUIDs can be obtained with *Client.uuid*, *Port.uuid* and *Client.get_uuid_for_client_name()*.

Returns

dict – A dictionary mapping property names to (value, type) tuples.

See also:

Client.set_property, *get_property*, *get_all_properties*, *Client.remove_property*,
Client.remove_properties, *Client.remove_all_properties*, *Client.set_property_change_callback*

jack.get_all_properties()

Get all properties for all subjects with metadata.

Returns

dict – A dictionary mapping UUIDs to nested dictionaries as returned by *get_properties()*.

See also:

Client.set_property, *get_property*, *get_properties*, *Client.remove_property*,
Client.remove_properties, *Client.remove_all_properties*, *Client.set_property_change_callback*

jack.position2dict(pos)

Convert CFFI position struct to a dict.

jack.version()

Get tuple of major/minor/micro/protocol version.

jack.version_string()

Get human-readable JACK version.

jack.client_name_size()

Return the maximum number of characters in a JACK client name.

This includes the final NULL character. This value is a constant.

jack.port_name_size()

Maximum length of port names.

The maximum number of characters in a full JACK port name including the final NULL character. This value is a constant.

A port's full name contains the owning client name concatenated with a colon (:) followed by its short name and a NULL character.

jack.set_error_function(callback=None)

Set the callback for error message display.

Set it to *None* to restore the default error callback function (which prints the error message plus a newline to stderr). The *callback* function must have this signature:

`callback(message: str) -> None`

jack.set_info_function(callback=None)

Set the callback for info message display.

Set it to *None* to restore default info callback function (which prints the info message plus a newline to stderr). The *callback* function must have this signature:

```
callback(message: str) -> None
```

`jack.client_pid(name)`

Return PID of a JACK client.

Parameters

name (*str*) – Name of the JACK client whose PID shall be returned.

Returns

int – PID of *name*. If not available, 0 will be returned.

5 Contributing

If you find bugs, errors, omissions or other things that need improvement, please create an issue or a pull request at <https://github.com/spatialaudio/jackclient-python>. Contributions are always welcome!

Instead of pip-installing the latest release from PyPI, you should get the newest development version from [Github](#)¹⁶:

```
git clone https://github.com/spatialaudio/jackclient-python.git
cd jackclient-python
python3 -m pip install -e .
```

... where `-e` stands for `--editable`. This way, your installation always stays up-to-date, even if you pull new changes from the Github repository.

Note: Whenever the file `jack_build.py` changes (either because you edited it or it was updated by pulling from Github or switching branches), you have to run the last command again.

If you make changes to the documentation, you can locally re-create the HTML pages using [Sphinx](#)¹⁷. You can install it and a few other necessary packages with:

```
python3 -m pip install -r doc/requirements.txt
```

To create the HTML pages, use:

```
python3 setup.py build_sphinx
```

The generated files will be available in the directory `build/sphinx/html/`.

There are no proper tests (yet?), but the code examples from the README file can be verified with [pytest](#)¹⁸. If you haven't installed it already, you can install it with:

```
python3 -m pip install pytest
```

As soon as [pytest](#)¹⁹ is installed, you can run the (rudimentary) tests with:

```
python3 -m pytest
```

¹⁶ <https://github.com/spatialaudio/jackclient-python/>

¹⁷ <https://www.sphinx-doc.org/>

¹⁸ <https://pytest.org/>

¹⁹ <https://pytest.org/>

6 Version History

Version 0.5.4 – 2022-06-04 – PyPI²⁰ – docs²¹ – diff²²

- drop Python 3.6 support

Version 0.5.3 – 2020-10-21 – PyPI²³ – docs²⁴ – diff²⁵

- use `jack_port_rename()` instead of deprecated `jack_port_set_name()`

Version 0.5.2 – 2020-02-11 – PyPI²⁶ – docs²⁷ – diff²⁸

- new module constants: `jack.POSITION_*`
- new examples: `timebase_master.py` and `transporter.py`, thanks to Christopher Arndt
- new `jack.JackError` subclasses: `jack.JackErrorCode` and `jack.JackOpenError`, thanks to Christopher Arndt

Version 0.5.1 – 2019-11-07 – PyPI²⁹ – docs³⁰ – diff³¹

- `jack.Client.release_timebase()`, thanks to Christopher Arndt

Version 0.5.0 – 2019-07-18 – PyPI³² – docs³³ – diff³⁴

- drop Python 2 support
- support for metadata API, with the help of Christopher Arndt
- support for slow-sync clients

Version 0.4.6 – 2019-02-09 – PyPI³⁵ – docs³⁶ – diff³⁷

- `midi_file_player.py` example

Version 0.4.5 – 2018-09-02 – PyPI³⁸ – docs³⁹ – diff⁴⁰

- Fix issue #54; other minor improvements

Version 0.4.4 – 2018-02-19 – PyPI⁴¹ – docs⁴² – diff⁴³

- `Port.set_alias()`, `Port.unset_alias()` and `Port.aliases`, thanks to José Fernando Moyano

Version 0.4.3 – 2017-12-30 – PyPI⁴⁴ – docs⁴⁵ – diff⁴⁶

²⁰ <https://pypi.org/project/JACK-Client/0.5.4/>

²¹ <https://jackclient-python.readthedocs.io/en/0.5.4/>

²² <https://github.com/spatialaudio/jackclient-python/compare/0.5.3...0.5.4>

²³ <https://pypi.org/project/JACK-Client/0.5.3/>

²⁴ <https://jackclient-python.readthedocs.io/en/0.5.3/>

²⁵ <https://github.com/spatialaudio/jackclient-python/compare/0.5.2...0.5.3>

²⁶ <https://pypi.org/project/JACK-Client/0.5.2/>

²⁷ <https://jackclient-python.readthedocs.io/en/0.5.2/>

²⁸ <https://github.com/spatialaudio/jackclient-python/compare/0.5.1...0.5.2>

²⁹ <https://pypi.org/project/JACK-Client/0.5.1/>

³⁰ <https://jackclient-python.readthedocs.io/en/0.5.1/>

³¹ <https://github.com/spatialaudio/jackclient-python/compare/0.5.0...0.5.1>

³² <https://pypi.org/project/JACK-Client/0.5.0/>

³³ <https://jackclient-python.readthedocs.io/en/0.5.0/>

³⁴ <https://github.com/spatialaudio/jackclient-python/compare/0.4.6...0.5.0>

³⁵ <https://pypi.org/project/JACK-Client/0.4.6/>

³⁶ <https://jackclient-python.readthedocs.io/en/0.4.6/>

³⁷ <https://github.com/spatialaudio/jackclient-python/compare/0.4.5...0.4.6>

³⁸ <https://pypi.org/project/JACK-Client/0.4.5/>

³⁹ <https://jackclient-python.readthedocs.io/en/0.4.5/>

⁴⁰ <https://github.com/spatialaudio/jackclient-python/compare/0.4.4...0.4.5>

⁴¹ <https://pypi.org/project/JACK-Client/0.4.4/>

⁴² <https://jackclient-python.readthedocs.io/en/0.4.4/>

⁴³ <https://github.com/spatialaudio/jackclient-python/compare/0.4.3...0.4.4>

⁴⁴ <https://pypi.org/project/JACK-Client/0.4.3/>

⁴⁵ <https://jackclient-python.readthedocs.io/en/0.4.3/>

⁴⁶ <https://github.com/spatialaudio/jackclient-python/compare/0.4.2...0.4.3>

- switch to CFFI out-of-line ABI mode (to reduce import time)

Version 0.4.2 – 2016-11-05 – [PyPI](#)^{47, 47} – [docs](#)⁴⁸ – [diff](#)⁴⁹

- new examples: `showtime.py`, `midi_sine_numpy.py` and `play_file.py`
- new option `only_available` for port callbacks

Version 0.4.1 – 2016-05-24 – [PyPI](#)⁵⁰ – [docs](#)⁵¹ – [diff](#)⁵²

- new property `jack.Client.transport_frame`, deprecating `jack.Client.transport_locate()`

Version 0.4.0 – 2015-09-17 – [PyPI](#)⁵³ – [docs](#)⁵⁴ – [diff](#)⁵⁵

- new argument to `xrun` callback (see `jack.Client.set_xrun_callback()`), `jack.Client.xrun_delayed_usecs` was removed
- `jack.Client.transport_reposition_struct()`
- callbacks no longer have to return anything, instead they can raise `jack.CallbackExit` on error
- `midi_sine.py` example

Version 0.3.0 – 2015-07-16 – [PyPI](#)⁵⁶ – [docs](#)⁵⁷ – [diff](#)⁵⁸

- `jack.RingBuffer`, implemented by Alexandru Stan
- `jack.Client.set_timebase_callback()`, `jack.Client.transport_query()`, `jack.Client.transport_query_struct()`, with the help of Julien Acroute
- `jack.Client.transport_state`, `jack.STOPPED`, `jack.ROLLING`, `jack.STARTING`, `jack.NETSTARTING`, `jack.position2dict()`
- the `userdata` argument was removed from all callbacks
- compatibility with the official JACK installer for Windows, thanks to Julien Acroute

Version 0.2.0 – 2015-02-23 – [PyPI](#)⁵⁹ – [docs](#)⁶⁰ – [diff](#)⁶¹

- MIDI support (`jack.MidiPort`, `jack.OwnMidiPort`, `jack.Client.midi_inports`, `jack.Client.midi_outports`, ...)
- ignore errors in `jack.Client.deactivate()` by default, can be overridden
- optional argument to `jack.OwnPort.disconnect()`
- several examples (`chatty_client.py`, `thru_client.py`, `midi_monitor.py` and `midi_chords.py`)
- `jack.Port.is_physical`, courtesy of Alexandru Stan
- `jack.Status`

Version 0.1.0 – 2014-12-15 – [PyPI](#)⁶² – [docs](#)⁶³

Initial release

⁴⁷ <https://pypi.org/project/JACK-Client/0.4.2/>

⁴⁸ <https://jackclient-python.readthedocs.io/en/0.4.2/>

⁴⁹ <https://github.com/spatialaudio/jackclient-python/compare/0.4.1...0.4.2>

⁵⁰ <https://pypi.org/project/JACK-Client/0.4.1/>

⁵¹ <https://jackclient-python.readthedocs.io/en/0.4.1/>

⁵² <https://github.com/spatialaudio/jackclient-python/compare/0.4.0...0.4.1>

⁵³ <https://pypi.org/project/JACK-Client/0.4.0/>

⁵⁴ <https://jackclient-python.readthedocs.io/en/0.4.0/>

⁵⁵ <https://github.com/spatialaudio/jackclient-python/compare/0.3.0...0.4.0>

⁵⁶ <https://pypi.org/project/JACK-Client/0.3.0/>

⁵⁷ <https://jackclient-python.readthedocs.io/en/0.3.0/>

⁵⁸ <https://github.com/spatialaudio/jackclient-python/compare/0.2.0...0.3.0>

⁵⁹ <https://pypi.org/project/JACK-Client/0.2.0/>

⁶⁰ <https://jackclient-python.readthedocs.io/en/0.2.0/>

⁶¹ <https://github.com/spatialaudio/jackclient-python/compare/0.1.0...0.2.0>

⁶² <https://pypi.org/project/JACK-Client/0.1.0/>

⁶³ <https://jackclient-python.readthedocs.io/en/0.1.0/>

7 Other Python Modules for JACK

7.1 JACK Client

PyJack

<https://sourceforge.net/projects/py-jack/>

jacklib from Cadence

<https://github.com/falkTX/Cadence/blob/master/src/jacklib.py>

pyjacklib (based on Cadence)

<https://github.com/jackaudio/pyjacklib>

jacker

<https://github.com/fphammerle/jacker>

7.2 JACK Server

jack_server

https://github.com/vrslev/jack_server

jackctl.py (part of JACK1)

<https://github.com/jackaudio/jack1/blob/master/python/jackctl.py>

7.3 D-Bus Interface (JACK2 only)

jack_control (part of JACK2)

https://github.com/jackaudio/jack2/blob/develop/dbus/jack_control

jackdbus (+ jack_re_connect CLI tool)

<https://github.com/romsom/python-jackdbus>